

OFFICIAL COURSE STUDY GUIDE

EKG Basics: Rhythm and 12-Lead Interpretation

From the electrical path of a single heartbeat to confident 12-lead reads.

HEALTHCARE & CAREGIVING · INTERMEDIATE · 5 MODULES · 12 HR 39 MIN

Course by ICU Advantage · Curated and published by MegaCourse

MEGACOURSE.APP

EKG Basics: Rhythm and 12-Lead Interpretation: The Complete Study Guide

2026 Edition

Published by MegaCourse · megacourse.app

Learn Anything. Achieve Everything.

MegaCourse curates the world's best free courses into structured learning paths with study guides, practice material, and certificates. This guide accompanies the MegaCourse course "EKG Basics: Rhythm and 12-Lead Interpretation", taught by ICU Advantage. It is designed to be read alongside the video lessons and to serve as a standalone reference for review.

Study guide text copyright © 2026 MegaCourse. Course video content remains the property of its creators. You may print this guide for personal study. Redistribution or resale is not permitted.

Enroll, track progress, and earn your certificate at

megacourse.app/courses/ekg-basics-rhythm-and-12-lead-interpretation

Contents

<i>About This Course</i>	4
CHAPTER 1 ECG Foundations	6
CHAPTER 2 12-Lead EKG Interpretation	12
CHAPTER 3 12-Lead EKG Interpretation	18
CHAPTER 4 Reading the EKG Strip	26
CHAPTER 5 Final Assessment: EKG Interpretation	31
<i>Glossary</i>	34
<i>Answer Key</i>	37
<i>Where to Go Next</i>	41

INTRODUCTION

About This Course

Welcome to "EKG Basics: Rhythm and 12-Lead Interpretation." This guide supports your learning path from understanding a single heartbeat's electrical path to confidently reading 12-lead EKGs. Mastering EKG interpretation is a fundamental skill in healthcare. It allows for rapid assessment of cardiac function and identification of critical conditions.

This course provides a structured learning path. It combines expert video instruction from ICU Advantage with additional curated resources, practice materials, and a final assessment. MegaCourse has organized the original content into 5 modules and 26 lessons, totaling about 12 hours and 39 minutes of instruction.

We have enhanced the original material by adding dedicated reading and resource lessons, a knowledge-check quiz, and a clear structure with defined learning outcomes. This comprehensive approach ensures you gain a solid foundation in EKG interpretation. You will develop a systematic method for analyzing cardiac rhythms and 12-lead tracings.

Course Facts

FORMAT	5 modules · 26 lessons
VIDEO INSTRUCTION	About 12 hr 39 min
LEVEL	Intermediate
CATEGORY	Healthcare & Caregiving
INSTRUCTOR	ICU Advantage
CERTIFICATE	Included with course completion on MegaCourse
COURSE HOME	megacourse.app/courses/ekg-basics-rhythm-and-12-lead-interpretation

What You Will Learn

- Explain the heart's conduction system and what each EKG waveform represents.
- Measure rate, rhythm, and intervals systematically on any strip.
- Identify sinus rhythms, blocks, and common lethal arrhythmias.
- Approach a 12-lead EKG with a repeatable interpretation method.

Who This Course Is For

This course is designed for healthcare students, aspiring clinicians, and current professionals seeking to build or refresh their EKG interpretation skills. It is suitable for anyone who needs to understand cardiac electrical activity and identify common arrhythmias. The content is presented at an intermediate level, providing both foundational knowledge and practical application.

Before beginning this course, you should have a basic understanding of human anatomy and common medical terminology. Familiarity with taking and interpreting vital signs will also be beneficial. This preparation will allow you to focus on the specific EKG concepts presented.

Before You Start

- Basic anatomy and medical terminology.
- Comfort with vital signs.

How to Use This Guide

This study guide is a companion to the video lessons provided by MegaCourse. We recommend watching each video lesson first. Then, use this guide to review key concepts, reinforce your understanding, and work through practice examples. The guide provides summaries, explanations, and additional context that complements the video instruction.

Each module is structured to build your knowledge progressively. Take your time to understand the material in one lesson before moving to the next. The course includes review sections and a final assessment. Use these tools to test your comprehension and identify areas needing further study. A glossary of terms is also available for quick reference.

Remember, this course is for educational content only. It does not confer clinical certification or licensure. It is not medical advice. Always follow your state's scope-of-practice regulations. In a real emergency, call 911.

CHAPTER 1

ECG Foundations

This chapter introduces the fundamental principles of electrocardiogram (ECG or EKG) interpretation. It begins by exploring the heart's intricate electrical conduction system, the origin of every heartbeat. You will learn how this electrical activity translates into the distinct waveforms observed on an EKG strip. Understanding these foundational concepts is crucial for accurate rhythm analysis.

The chapter then progresses to a systematic approach for interpreting EKG rhythms. You will practice measuring key intervals and identifying normal versus abnormal patterns. We will cover common arrhythmias, including various sinus rhythms, atrial fibrillation, atrial flutter, junctional rhythms, and life-threatening ventricular arrhythmias. Finally, we will examine the different types of heart blocks. By the end of this chapter, you will possess a solid understanding of basic EKG interpretation, preparing you for more advanced topics.

The Heart's Electrical System and EKG Basics

Covers: Electrical Conduction System of the Heart | ECG EKG Interpretation (Part 1) · ECG Interpretation Made Easy | ECG EKG Interpretation (Part 2)

The heart is a remarkable pump, driven by its own intrinsic electrical system. This system ensures coordinated contraction, pushing blood throughout the body. Understanding this electrical pathway is the first step in EKG interpretation.

The Conduction Pathway

Electrical impulses originate in the **sinoatrial (SA) node**, located in the right atrium. The SA node is the heart's natural pacemaker, typically firing 60 to 100 times per minute. From the SA node, the impulse spreads across both atria, causing them to depolarize and contract. This atrial depolarization is represented by the **P wave** on the EKG.

The impulse then reaches the **atrioventricular (AV) node**, located near the interatrial septum. The AV node briefly delays the impulse, allowing the atria to fully empty blood into the ventricles before ventricular contraction. This delay is seen as the **PR interval** on the EKG, which measures the time from the start of atrial depolarization to the start of ventricular depolarization. A normal PR interval is 0.12 to 0.20 seconds (3 to 5 small squares).

After the AV node, the impulse travels rapidly down the **Bundle of His**, divides into the left and right **bundle branches**, and then spreads through the **Purkinje fibers** into the ventricular muscle. This rapid spread causes ventricular depolarization and contraction, represented by the **QRS complex** on the EKG. The QRS complex typically lasts 0.06 to 0.12 seconds (1.5 to 3 small squares).

Finally, the ventricles repolarize, meaning they reset electrically to prepare for the next beat. This ventricular repolarization is represented by the **T wave** on the EKG. Atrial repolarization also occurs, but

it is usually hidden within the larger QRS complex.

EKG Paper and Measurements

EKG paper is a grid of small and large squares. Each small square is 1 millimeter (mm) by 1 mm. Each large square consists of five small squares horizontally and five small squares vertically. The horizontal axis measures time, and the vertical axis measures voltage.

- **Horizontal Axis (Time):**
 - One small square = 0.04 seconds
 - One large square (5 small squares) = 0.20 seconds
 - 300 large squares = 1 minute
- **Vertical Axis (Voltage):**
 - One small square = 0.1 millivolt (mV)
 - One large square (5 small squares) = 0.5 mV

Accurate measurement of intervals and waveforms is fundamental. Always count the number of small squares and multiply by 0.04 seconds for time measurements. For example, if a QRS complex spans 2.5 small squares, its duration is $2.5 * 0.04 \text{ seconds} = 0.10 \text{ seconds}$. Common mistakes involve miscounting squares or forgetting the 0.04 second conversion factor. Practice identifying each wave and measuring its corresponding interval precisely.

Systematic EKG Interpretation and Sinus Rhythms

Covers: Basic Arrhythmias | Sinus, Brady, Tachy, Premature Beats | ECG EKG Interpretation (Part 3)

A systematic approach is essential for accurate EKG interpretation. Following a consistent checklist helps prevent overlooking critical details. Here is a common method:

The Six-Step Interpretation Method

1. **Rate:** Determine the heart rate. For regular rhythms, count the number of large squares between two R waves and divide 300 by that number. Alternatively, count the number of R waves in a 6-second strip (30 large squares) and multiply by 10. For irregular rhythms, the 6-second method is more reliable.
 - *Example (300 method):* If 4 large squares separate two R waves, the rate is $300 / 4 = 75$ beats per minute (bpm).
 - *Example (6-second method):* If you count 8 R waves in a 6-second strip, the rate is $8 * 10 = 80$ bpm.
2. **Rhythm:** Is the rhythm regular or irregular? Measure the R-R intervals across the strip. If they are consistent, the rhythm is regular. If they vary, it is irregular.
3. **P Waves:** Are P waves present? Do they occur before every QRS complex? Are they upright and uniform? Do all P waves look alike?
4. **PR Interval:** Measure the PR interval. Is it within the normal range of 0.12 to 0.20 seconds? Is it constant across the strip?

5. **QRS Duration:** Measure the QRS duration. Is it within the normal range of 0.06 to 0.12 seconds? Is it constant across the strip?
6. **QT Interval:** Measure the QT interval. This interval represents the total time for ventricular depolarization and repolarization. It varies with heart rate, so a corrected QT (QTc) is often used. A normal QT interval is typically less than half the R-R interval. Prolonged QT can indicate a risk for dangerous arrhythmias.

Sinus Rhythms

Normal Sinus Rhythm (NSR) is the baseline for comparison. It meets all normal criteria:

- Rate: 60 to 100 bpm
- Rhythm: Regular
- P waves: Present, upright, uniform, one before each QRS
- PR interval: 0.12 to 0.20 seconds, constant
- QRS duration: 0.06 to 0.12 seconds, constant

Variations of sinus rhythm include:

- **Sinus Bradycardia:** Rate less than 60 bpm, but all other NSR criteria met.
- **Sinus Tachycardia:** Rate greater than 100 bpm, but all other NSR criteria met.
- **Sinus Arrhythmia:** Irregular rhythm that varies with respiration, often speeding up with inspiration and slowing with expiration. All other NSR criteria met.

Premature Beats

- **Premature Atrial Contractions (PACs):** An early beat originating from an ectopic focus in the atria. It has an abnormal P wave (different shape or hidden in the preceding T wave) followed by a normal QRS. The underlying rhythm is often sinus.
- **Premature Ventricular Contractions (PVCs):** An early, wide, and bizarre QRS complex not preceded by a P wave. PVCs originate from an ectopic focus in the ventricles. They can be unifocal (all look the same) or multifocal (different shapes). Common mistakes include confusing PVCs with aberrantly conducted supraventricular beats.

Atrial and Junctional Arrhythmias

Covers: Afib, Aflutter, Junctional Arrhythmias | ECG EKG Interpretation (Part 4)

Beyond basic sinus rhythms, several arrhythmias originate in the atria or the AV junction. These can range from relatively benign to clinically significant, requiring careful identification.

Atrial Fibrillation (Afib)

Atrial fibrillation is a common and often serious arrhythmia characterized by chaotic electrical activity in the atria. Instead of a single impulse from the SA node, multiple disorganized impulses fire rapidly, causing the atria to quiver rather than contract effectively. Key EKG characteristics include:

- **Rate:** Atrial rate is extremely fast and unmeasurable (350 to 600 bpm). Ventricular rate (the QRS rate) is irregularly irregular, often rapid (greater than 100 bpm) if uncontrolled, or normal to slow if controlled.
- **Rhythm:** Irregularly irregular. The R-R intervals show no discernible pattern.
- **P waves:** Absent. Instead, you will see fine to coarse fibrillatory waves (f waves) that appear as a wavy baseline.
- **PR interval:** Not measurable due to absent P waves.
- **QRS duration:** Usually normal (0.06 to 0.12 seconds), unless there is an underlying conduction defect.

Atrial Flutter (Aflutter)

Atrial flutter is caused by a re-entrant circuit in the atria, typically in the right atrium, producing rapid, regular atrial depolarizations. This creates a distinct 'sawtooth' pattern on the EKG, especially visible in leads II, III, and aVF.

- **Rate:** Atrial rate is typically 250 to 350 bpm. Ventricular rate depends on the AV node's conduction ratio (e.g., 2:1, 3:1, 4:1 block). If the atrial rate is 300 bpm and there is a 2:1 block, the ventricular rate is 150 bpm.
- **Rhythm:** Atrial rhythm is regular. Ventricular rhythm can be regular (if the block ratio is constant) or irregular (if the block ratio varies).
- **P waves:** Absent. Replaced by distinct, uniform flutter waves (F waves) that resemble a sawtooth pattern.
- **PR interval:** Not measurable.
- **QRS duration:** Usually normal.

Junctional Rhythms

Junctional rhythms originate in the AV node or the Bundle of His when the SA node fails to fire or its impulse is blocked. The AV node acts as a secondary pacemaker.

- **Rate:** The intrinsic rate of the AV node is 40 to 60 bpm. If the rate is 60 to 100 bpm, it is an **accelerated junctional rhythm**. If it is over 100 bpm, it is **junctional tachycardia**.
- **Rhythm:** Usually regular.
- **P waves:** May be absent, inverted (upside down) before the QRS, or inverted after the QRS (retrograde conduction). This is because the atria are depolarized from the AV node upwards.
- **PR interval:** If P waves are present before the QRS, the PR interval will be short (less than 0.12 seconds).
- **QRS duration:** Usually normal.

When interpreting these rhythms, pay close attention to the presence and appearance of P waves and the regularity of the R-R interval. These are key differentiators.

Ventricular Arrhythmias and Heart Blocks

Covers: Ventricular Arrhythmias | ECG EKG Interpretation (Part 5) · Heart Blocks Made Easy | ECG EKG Interpretation (Part 6)

Ventricular arrhythmias are often life-threatening because they compromise the heart's pumping ability. Heart blocks, on the other hand, represent impaired conduction through the AV node or below, leading to delays or complete interruptions in the electrical signal from the atria to the ventricles.

Ventricular Arrhythmias

- **Ventricular Tachycardia (VT):** A rapid, regular rhythm originating from the ventricles. It is characterized by wide, bizarre QRS complexes. VT can be monomorphic (all QRS complexes look the same) or polymorphic (QRS complexes vary in shape). A rate of 100 to 250 bpm is common. VT can quickly deteriorate into ventricular fibrillation and requires immediate medical attention.
- **Ventricular Fibrillation (VF):** A chaotic, disorganized electrical activity in the ventricles, leading to ventricular quivering rather than effective contraction. On the EKG, VF appears as irregular, undulating waveforms with no discernible P waves, QRS complexes, or T waves. The patient is pulseless and requires immediate defibrillation.
- **Asystole:** Complete absence of electrical activity in the ventricles. The EKG shows a flat line. This is a cardiac arrest rhythm and requires immediate cardiopulmonary resuscitation (CPR) and advanced life support.

Heart Blocks

Heart blocks are categorized based on the degree of conduction impairment between the atria and ventricles. They are typically classified as first-degree, second-degree (Type I and Type II), and third-degree.

- **First-Degree AV Block:** This is a delay in conduction through the AV node, not a complete block. Every atrial impulse reaches the ventricles. The key characteristic is a **prolonged PR interval (greater than 0.20 seconds)** that remains constant. All other EKG parameters are usually normal.
- **Second-Degree AV Block Type I (Wenckebach):** This block is characterized by a progressively lengthening PR interval until a QRS complex is dropped. The pattern then repeats. The atrial rhythm is regular, but the ventricular rhythm is irregular due to the dropped beats. The R-R interval progressively shortens before the dropped beat.
- **Second-Degree AV Block Type II:** This block involves intermittent, sudden drops of QRS complexes without prior PR interval prolongation. The PR interval of conducted beats remains constant and within normal limits. The atrial rhythm is regular, but the ventricular rhythm is irregular. This type of block is more serious as it can progress to third-degree block.
- **Third-Degree AV Block (Complete Heart Block):** In this block, there is a complete dissociation between atrial and ventricular activity. No atrial impulses are conducted to the ventricles. The atria and ventricles beat independently. The EKG shows regular P waves at an atrial rate (e.g., 60-100 bpm) and regular QRS complexes at a slower ventricular escape rate (e.g., 20-40 bpm for a ventricular

escape rhythm, or 40-60 bpm for a junctional escape rhythm). There is no relationship between the P waves and QRS complexes. This is a medical emergency.

KEY TAKEAWAYS

- The heart's electrical impulse originates in the SA node, travels through the atria, pauses at the AV node, and then rapidly spreads through the ventricles.
- The P wave represents atrial depolarization, the QRS complex represents ventricular depolarization, and the T wave represents ventricular repolarization.
- EKG paper measures time horizontally (0.04 seconds per small square) and voltage vertically (0.1 mV per small square).
- A systematic six-step approach (rate, rhythm, P waves, PR interval, QRS duration, QT interval) is crucial for accurate EKG interpretation.
- Normal Sinus Rhythm is the standard, with variations like sinus bradycardia and tachycardia reflecting rate changes.
- Atrial Fibrillation is marked by an irregularly irregular rhythm and absent P waves replaced by fibrillatory waves.
- Atrial Flutter presents with a characteristic 'sawtooth' pattern of flutter waves and a regular atrial rhythm.
- Ventricular Tachycardia and Fibrillation are dangerous rhythms originating in the ventricles, requiring urgent intervention.
- Heart blocks involve impaired conduction between atria and ventricles, ranging from a prolonged PR interval (first-degree) to complete dissociation (third-degree).

CHECK YOUR UNDERSTANDING

Answer these before moving on. Model answers are in the Answer Key at the back of this guide.

1. Describe the normal electrical pathway through the heart, starting from the SA node.
2. What EKG waveform or interval corresponds to atrial depolarization, ventricular depolarization, and ventricular repolarization?
3. You see an EKG strip with an atrial rate of 300 bpm and a ventricular rate of 150 bpm, with a 'sawtooth' baseline. What rhythm is this, and what is the AV conduction ratio?
4. A patient's EKG shows a regular rhythm, a heart rate of 55 bpm, and all other EKG parameters (P waves, PR interval, QRS duration) are within normal limits. What is the most likely rhythm?
5. What are the key EKG characteristics that differentiate a first-degree AV block from a second-degree AV block Type I (Wenckebach)?

CHAPTER 2

12-Lead EKG Interpretation

This chapter builds on your foundational understanding of EKG basics. It moves beyond single-lead rhythm strips to the comprehensive view offered by a 12-lead EKG. You will learn about the heart's blood supply and electrical system, essential for understanding EKG changes. This chapter introduces the systematic steps for interpreting a 12-lead EKG. It also covers common abnormalities such as bundle branch blocks, cardiac axis deviations, and atrial enlargement. Mastering these concepts is crucial for accurate EKG assessment.

Foundations of Cardiac Function and EKG Introduction

Covers: The Anatomy of the Coronary Circulation · What is the PHYSIOLOGY of the coronary circulation? · The Electrical Conduction System of the Heart EXPLAINED! · Introduction to Concepts of 12-Lead EKG Interpretation

The heart is a pump, and like any pump, it requires its own fuel and a precise electrical system to function. Understanding the heart's blood supply, known as the coronary circulation, is fundamental to interpreting many EKG abnormalities. The heart muscle, or myocardium, receives oxygenated blood from the coronary arteries. The two main coronary arteries are the Left Main Coronary Artery and the Right Coronary Artery. The Left Main Coronary Artery quickly branches into the Left Anterior Descending (LAD) artery, which supplies the anterior wall and septum, and the Circumflex artery, which supplies the lateral and posterior walls. The Right Coronary Artery (RCA) typically supplies the inferior wall and often the posterior wall, as well as the SA and AV nodes in most individuals. When blood flow through these arteries is reduced or blocked, the affected myocardial tissue becomes ischemic, injured, or infarcted. These changes are directly observable on an EKG. For example, ST segment elevation often indicates acute myocardial infarction, or heart attack, due to a complete blockage in a coronary artery. ST depression or T wave inversion can suggest myocardial ischemia, meaning reduced blood flow.

The heart's electrical conduction system is the engine that drives its rhythmic contractions. This specialized network ensures a coordinated and efficient pump. The path begins at the sinoatrial (SA) node, located in the right atrium. The SA node is the heart's natural pacemaker, generating electrical impulses at a rate of 60 to 100 beats per minute. These impulses spread across both atria, causing them to contract and pushing blood into the ventricles. As the impulse reaches the atrioventricular (AV) node, located near the interatrial septum, it experiences a brief delay. This delay is crucial. It allows time for the ventricles to fully fill with blood before they contract. From the AV node, the impulse travels rapidly down the Bundle of His, which then divides into the left and right bundle branches. These branches further divide into a network of Purkinje fibers that penetrate the ventricular muscle. The Purkinje fibers ensure rapid and synchronous depolarization of the ventricles, leading to a powerful contraction that ejects blood into the systemic and pulmonary circulations.

A 12-lead EKG provides a comprehensive view of this electrical activity. Unlike a single-lead rhythm strip, which offers only one perspective, the 12-lead EKG uses 10 electrodes placed on the patient's limbs and chest to generate 12 different electrical "pictures" or leads. These leads are grouped to view specific areas

of the heart. The limb leads (I, II, III, aVR, aVL, aVF) primarily view the frontal plane, providing information about the heart's overall electrical direction, known as the cardiac axis. The chest, or precordial, leads (V1, V2, V3, V4, V5, V6) view the horizontal plane. They offer detailed information about the anterior, septal, and lateral walls of the ventricles.

Each EKG waveform represents a specific electrical event. The P wave signifies atrial depolarization, the electrical activation of the atria. The QRS complex represents ventricular depolarization, the electrical activation of the ventricles. The T wave represents ventricular repolarization, the electrical recovery of the ventricles. Understanding the normal appearance and timing of these waveforms in all 12 leads is the first step toward identifying abnormalities. The concept of electrical vectors is key here. Each lead acts like a camera, recording the electrical activity as it moves toward or away from it. A positive deflection occurs when the electrical current moves toward a positive electrode, and a negative deflection occurs when it moves away. This multi-angle perspective allows for precise localization of cardiac issues.

Systematic 12-Lead EKG Interpretation

Covers: The SIMPLE Steps of 12-Lead EKG Interpretation - EXPLAINED CLEARLY!

Interpreting a 12-lead EKG requires a systematic, step-by-step approach to ensure no critical information is missed. Rushing or skipping steps can lead to misdiagnosis. This structured method helps you consistently analyze all aspects of the EKG.

Here are the simple steps for 12-lead EKG interpretation:

- 1. Standardization Check:** First, examine the calibration marks. The standard calibration should show a deflection of 10 small boxes vertically (1 mV) and a paper speed of 25 mm/second. This ensures accurate amplitude and timing measurements. If the EKG is not standardized correctly, measurements will be inaccurate.
- 2. Rate Determination:** Calculate the heart rate. For a regular rhythm, count the number of large boxes between two R waves and divide 300 by that number. For irregular rhythms, count the number of QRS complexes in a 6-second strip (30 large boxes) and multiply by 10. Normal rate is 60 to 100 beats per minute.
- 3. Rhythm Analysis:** Determine if the rhythm is regular or irregular. Look for P waves before every QRS complex. Are the P waves upright in lead II? Is the PR interval consistent? Is the QRS complex narrow or wide? Identify the underlying rhythm, such as sinus rhythm, atrial fibrillation, or a junctional rhythm.
- 4. Interval Measurement:**
 - **PR Interval:** Measure from the beginning of the P wave to the beginning of the QRS complex. Normal is 0.12 to 0.20 seconds (3 to 5 small boxes). A prolonged PR interval indicates a first-degree AV block.
 - **QRS Duration:** Measure from the beginning of the Q wave (or R wave if no Q) to the end of the S wave. Normal is 0.06 to 0.10 seconds (1.5 to 2.5 small boxes). A wide QRS can indicate a bundle branch block, ventricular rhythm, or hyperkalemia.

- **QT Interval:** Measure from the beginning of the QRS complex to the end of the T wave. The QT interval is rate-dependent, so it is often corrected (QTc). Normal QTc is typically less than 0.44 seconds in men and 0.46 seconds in women. Prolonged QT can lead to dangerous arrhythmias.
5. **Axis Determination:** Determine the mean electrical axis of the ventricles. The easiest method is the quadrant approach using leads I and aVF.
 - If QRS is positive in I and positive in aVF, the axis is normal (0 to +90 degrees).
 - If QRS is positive in I and negative in aVF, the axis is Left Axis Deviation (LAD) (0 to -90 degrees).
 - If QRS is negative in I and positive in aVF, the axis is Right Axis Deviation (RAD) (+90 to +180 degrees).
 - If QRS is negative in I and negative in aVF, the axis is Extreme Right Axis Deviation (or "Northwest Axis") (-90 to -180 degrees).
 6. **Hypertrophy and Enlargement:** Look for signs of atrial enlargement (P wave morphology) or ventricular hypertrophy (increased QRS voltage, strain patterns). Specific criteria exist for Left Ventricular Hypertrophy (LVH) and Right Ventricular Hypertrophy (RVH).
 7. **Ischemia, Injury, and Infarction:** This is a critical step.
 - **Ischemia:** Look for T wave inversions or ST segment depression.
 - **Injury (Acute MI):** Look for ST segment elevation in two or more contiguous leads.
 - **Infarction (Old MI):** Look for pathological Q waves (at least 1 small box wide or 1/3 the height of the R wave) in two or more contiguous leads. Identify the location of changes (e.g., inferior, anterior, lateral, septal).
 8. **Other Abnormalities:** Finally, look for any other findings such as bundle branch blocks, specific arrhythmias, electrolyte disturbances, or drug effects.

Consistently following these steps ensures a thorough and accurate interpretation of every 12-lead EKG.

Specific EKG Abnormalities: Blocks, Axis, and Enlargement

Covers: Bundle Branch Blocks MADE EASY!! - 12 Lead EKG · Understanding Cardiac Axis and Deviations - 12-Lead EKG · IDENTIFY Atrial Enlargement on 12-Lead EKG

Beyond the basic systematic interpretation, recognizing specific patterns on a 12-lead EKG allows for the diagnosis of particular conditions. This section focuses on three key abnormalities: bundle branch blocks, cardiac axis deviations, and atrial enlargement.

Bundle Branch Blocks

Bundle branch blocks (BBBs) occur when there is a delay or interruption in the electrical conduction through either the right or left bundle branch. This forces the impulse to travel through the myocardium in an abnormal, slower path, resulting in a widened QRS complex.

- **Right Bundle Branch Block (RBBB):**

- **Key features:** QRS duration is 0.12 seconds or greater (three small boxes).
- There is an "RSR'" pattern, often described as an "M" shape, in lead V1. This indicates delayed depolarization of the right ventricle.
- A wide, slurred S wave appears in leads I and V6.
- T wave inversions may be seen in V1-V3, which are typically secondary repolarization abnormalities and not indicative of ischemia.
- RBBB can be a normal variant in some individuals, but it can also be associated with conditions like pulmonary embolism, right ventricular hypertrophy, or myocardial infarction.
- **Left Bundle Branch Block (LBBB):**
- **Key features:** QRS duration is 0.12 seconds or greater.
- A broad, notched, or slurred R wave appears in leads I, aVL, and V5-V6. This often creates a "W" shape in V1 and an "M" shape in V6.
- Absence of Q waves in leads I, V5, and V6.
- T wave inversions and ST segment depression are common in the lateral leads (I, aVL, V5, V6) and are considered secondary changes.
- LBBB is usually a sign of underlying heart disease and can obscure the diagnosis of acute myocardial infarction, making EKG interpretation more challenging in these patients.

Cardiac Axis and Deviations

The cardiac axis represents the average direction of the electrical forces generated by the ventricles during depolarization. It is typically expressed in degrees. A normal axis ranges from -30 to +90 degrees. Deviations from this normal range can indicate various cardiac pathologies.

- **Normal Axis:** QRS is predominantly positive (upright) in both lead I and lead aVF.
- **Left Axis Deviation (LAD):** QRS is predominantly positive in lead I but predominantly negative (downward) in lead aVF. The axis is shifted to the left, typically between -30 and -90 degrees. Common causes include left ventricular hypertrophy, inferior myocardial infarction, or left anterior fascicular block.
- **Right Axis Deviation (RAD):** QRS is predominantly negative in lead I but predominantly positive in lead aVF. The axis is shifted to the right, typically between +90 and +180 degrees. Common causes include right ventricular hypertrophy, acute pulmonary embolism, or lateral myocardial infarction.
- **Extreme Right Axis Deviation (Northwest Axis):** QRS is predominantly negative in both lead I and lead aVF. This is a rare and often serious finding, associated with conditions like ventricular tachycardia or hyperkalemia.

To determine axis quickly, use the quadrant method with leads I and aVF. If either is equivocal, use lead II. If lead II is positive, the axis is likely normal or LAD. If lead II is negative, the axis is likely RAD or extreme RAD.

Atrial Enlargement

Enlargement of the atria can also be detected on a 12-lead EKG by changes in the P wave morphology.

- **Right Atrial Enlargement (RAE) or P-pulmonale:**
 - Characterized by a tall, peaked P wave (greater than 2.5 mm in height) in lead II.
 - The P wave in V1 may be biphasic, with an initial tall, positive component.
 - RAE is often associated with conditions that increase pressure in the right atrium, such as chronic lung disease (e.g., COPD) or pulmonary hypertension.
- **Left Atrial Enlargement (LAE) or P-mitrale:**
 - Characterized by a broad, notched P wave (duration greater than 0.12 seconds, or three small boxes) in lead II. This is often described as an "M" shape.
 - The P wave in V1 may be biphasic, with a prominent, wide, negative terminal component (greater than 1 small box deep and 1 small box wide).
 - LAE is commonly associated with conditions that increase pressure in the left atrium, such as mitral valve disease (e.g., mitral stenosis or regurgitation), left ventricular hypertrophy, or hypertension.

Recognizing these specific patterns is a crucial step in advanced EKG interpretation. They provide valuable clues about the patient's underlying cardiac health.

KEY TAKEAWAYS

- The coronary circulation provides vital blood supply to the heart muscle, and disruptions manifest on an EKG.
- The heart's electrical conduction system generates and propagates impulses, forming the basis of EKG waveforms.
- A 12-lead EKG offers multiple views of the heart's electrical activity, allowing for comprehensive assessment.
- Systematic interpretation of a 12-lead EKG involves analyzing rate, rhythm, axis, intervals, and specific waveform changes.
- Bundle branch blocks are identified by widened QRS complexes and characteristic morphology in specific leads.
- Cardiac axis reflects the net direction of ventricular depolarization, with deviations indicating underlying cardiac conditions.
- Atrial enlargement can be detected by specific P wave changes in leads II and V1.

CHECK YOUR UNDERSTANDING

Answer these before moving on. Model answers are in the Answer Key at the back of this guide.

1. Describe the primary function of the coronary circulation and how it relates to EKG interpretation.
2. What are the main components of the heart's electrical conduction system, and what is the role of each?
3. Outline the basic systematic steps for interpreting a 12-lead EKG.
4. How do you identify a Right Bundle Branch Block (RBBB) on a 12-lead EKG?
5. Explain the significance of cardiac axis deviation.

CHAPTER 3

12-Lead EKG Interpretation

This chapter builds on your foundational understanding of EKG interpretation, focusing on advanced concepts in 12-lead EKG analysis. You will learn to identify key EKG changes associated with ventricular hypertrophy, myocardial ischemia, and acute myocardial infarction (AMI). We will cover the specific criteria for recognizing ST Elevation Myocardial Infarction (STEMI), including strategies to differentiate true STEMI from common mimics.

Also, this chapter introduces specialized criteria, such as Sgarbossa's, for interpreting AMI in the presence of confounding conditions like Left Bundle Branch Block (LBBB). The goal is to equip you with a systematic and comprehensive approach to confidently interpret 12-lead EKGs, integrating all the knowledge gained throughout the course.

Recognizing Ventricular Hypertrophy on 12-Lead EKG

Covers: Ventricular Hypertrophy (LVH & RVH) on 12-Lead EKG (video, 22 min)

Ventricular hypertrophy refers to the thickening of the muscular walls of the heart's ventricles. This condition often develops in response to increased workload, such as chronic hypertension (leading to Left Ventricular Hypertrophy, LVH) or pulmonary hypertension (leading to Right Ventricular Hypertrophy, RVH). While echocardiography is the gold standard for diagnosing hypertrophy, the 12-lead EKG provides valuable clues.

Left Ventricular Hypertrophy (LVH)

LVH is more common and often associated with characteristic voltage criteria and repolarization abnormalities. The increased muscle mass generates larger electrical forces, resulting in taller R waves in leads overlying the left ventricle and deeper S waves in leads overlying the right ventricle.

Common EKG criteria for LVH include:

- **Sokolow-Lyon Criteria:** The sum of the S wave depth in lead V1 or V2 plus the R wave height in lead V5 or V6 is greater than 35 mm (3.5 large boxes). This is a widely used and relatively simple criterion.
- **Cornell Criteria:** The sum of the R wave height in lead aVL plus the S wave depth in lead V3 is greater than 28 mm for men or greater than 20 mm for women. This criterion considers gender differences.
- **R wave in aVL:** An R wave height in lead aVL greater than 11 mm.

Beyond voltage, LVH often presents with a 'strain pattern' in the lateral leads (I, aVL, V5, V6). This pattern includes downsloping ST segment depression and asymmetrical T wave inversion, which are secondary repolarization abnormalities caused by altered repolarization in the hypertrophied muscle. It is crucial to distinguish this benign strain pattern from acute ischemia.

Right Ventricular Hypertrophy (RVH)

RVH is less common than LVH and typically harder to diagnose with EKG alone. It often results from conditions that increase the workload on the right ventricle, such as severe lung disease or pulmonary embolism. The EKG findings reflect the increased electrical activity of the right ventricle.

Common EKG criteria for RVH include:

- **Right Axis Deviation (RAD):** The QRS axis is typically greater than +90 degrees.
- **Tall R wave in V1:** An R wave in lead V1 that is taller than the S wave (R/S ratio > 1 in V1). An R wave height in V1 greater than 7 mm is also suggestive.
- **Deep S wave in V5 or V6:** An S wave in V5 or V6 that is deeper than the R wave (R/S ratio < 1 in V5 or V6).
- **ST segment depression and T wave inversion:** These secondary repolarization abnormalities may be seen in the right precordial leads (V1-V3), similar to the strain pattern in LVH.

It is important to remember that EKG criteria for hypertrophy, especially RVH, have limitations in sensitivity and specificity. They serve as indicators that warrant further investigation. Always correlate EKG findings with the patient's clinical presentation and other diagnostic tests. A systematic approach involves first checking for voltage criteria, then looking for associated repolarization changes, and finally considering axis deviation.

Foundations of Myocardial Ischemia and Infarction

Covers: The ST Segment and T Wave REVIEW (video, 13 min) · Introductory Concepts for Acute Myocardial Infarction (AMI) on 12-Lead EKG (video, 14 min)

Understanding the ST segment and T wave is fundamental to identifying myocardial ischemia and infarction. The ST segment represents the period when the ventricles are fully depolarized, occurring between the end of the QRS complex (J point) and the beginning of the T wave. Normally, the ST segment is isoelectric, meaning it lies on the baseline. The T wave represents ventricular repolarization, the electrical recovery of the ventricles. It is typically upright and asymmetrical in most leads, with the exception of aVR and V1, where it can be inverted.

Changes in the ST segment and T wave are the primary EKG indicators of myocardial ischemia, injury, and infarction. These conditions fall under the umbrella of Acute Coronary Syndromes (ACS), which result from a sudden reduction in blood flow to a part of the heart muscle.

Acute Myocardial Infarction (AMI) Concepts

An Acute Myocardial Infarction (AMI), commonly known as a heart attack, occurs when a prolonged lack of blood supply (ischemia) leads to irreversible damage and death of heart muscle tissue. It is a critical medical emergency requiring immediate intervention. The 12-lead EKG plays a pivotal role in the rapid diagnosis and management of AMI, particularly in distinguishing between ST Elevation Myocardial Infarction (STEMI) and Non-ST Elevation Myocardial Infarction (NSTEMI).

The progression of myocardial damage can be conceptualized in three stages, each with distinct EKG manifestations:

1. **Ischemia:** This is a reversible state where heart muscle receives insufficient blood flow. EKG changes typically include ST segment depression or T wave inversion. These changes reflect altered repolarization due to inadequate oxygen supply.
2. **Injury:** If ischemia is prolonged, it progresses to myocardial injury. This stage is characterized by ST segment elevation. The elevated ST segment indicates that a portion of the heart muscle is acutely injured and unable to repolarize normally. This is a hallmark of STEMI.
3. **Infarction:** If the injury persists without restoration of blood flow, irreversible cell death occurs, leading to infarction. EKG evidence of infarction includes the development of pathological Q waves. These Q waves represent areas of electrically silent necrotic tissue, as the electrical impulse moves away from the infarcted area.

The EKG changes are dynamic and evolve over time. Initially, hyperacute T waves (tall, peaked T waves) may be seen, followed by ST elevation. Over hours to days, pathological Q waves develop, and ST elevation may resolve, replaced by T wave inversion. Recognizing this evolution is crucial for dating an infarction and guiding treatment decisions. The presence of reciprocal changes, where ST depression occurs in leads opposite to those with ST elevation, further supports the diagnosis of an acute coronary event.

Identifying Myocardial Ischemia and ST Elevation Myocardial Infarction (STEMI)

Covers: Myocardial Ischemia - ST Depression & T Wave Inversion - 12-lead EKG (video, 13 min) · Recognize ST Elevation Myocardial Infarction (STEMI) on 12-lead EKG! (video, 23 min)

Accurate identification of myocardial ischemia and ST Elevation Myocardial Infarction (STEMI) on a 12-lead EKG is critical for timely patient care. These conditions manifest with specific and often dramatic EKG changes.

Myocardial Ischemia

Myocardial ischemia, a reversible condition of reduced blood flow to the heart muscle, typically presents with two primary EKG changes:

- **ST Segment Depression:** This is a key indicator of subendocardial ischemia, meaning the inner layer of the heart muscle is affected. Significant ST depression is defined as horizontal or downsloping ST segment depression of 0.5 mm (0.5 small boxes) or more, measured at the J point, in two or more contiguous leads. Upsloping ST depression is less specific for ischemia.
- **T Wave Inversion:** Symmetrical T wave inversion of 1 mm or more in two or more contiguous leads is also indicative of ischemia. It reflects altered repolarization. Deep, symmetrical T wave inversions, especially in the anterior leads, can be a sign of severe ischemia (e.g., Wellens' syndrome, indicating critical stenosis of the left anterior descending artery).

Contiguous leads are those that look at the same anatomical area of the heart. For example, leads II, III, and aVF are contiguous (inferior wall), as are V1-V4 (anterior/septal), I, aVL, V5, and V6 (lateral).

ST Elevation Myocardial Infarction (STEMI)

STEMI represents transmural myocardial injury, affecting the full thickness of the heart muscle, usually due to a complete occlusion of a coronary artery. It is diagnosed by significant ST segment elevation in two or more contiguous leads.

Specific criteria for significant ST elevation are:

- **In leads V2-V3:**
 - Greater than or equal to 2 mm (2 small boxes) in men 40 years or older.
 - Greater than or equal to 2.5 mm in men younger than 40 years.
 - Greater than or equal to 1.5 mm in women of any age.
- **In all other leads (I, II, III, aVL, aVF, V1, V4, V5, V6):** Greater than or equal to 1 mm (1 small box).

ST elevation is measured at the J point, which is the junction between the end of the QRS complex and the beginning of the ST segment. The morphology of the ST elevation is also important; it is often convex (domed) or straight in STEMI, contrasting with the concave (scooped) elevation seen in benign early repolarization.

Pathological Q Waves

While ST elevation indicates acute injury, pathological Q waves develop hours to days after the onset of infarction and signify irreversible myocardial necrosis. Criteria for pathological Q waves include:

- Duration of 0.04 seconds (one small box) or more.
- Depth of at least one-third the height of the R wave in the same QRS complex.
- Present in two or more contiguous leads.

Pathological Q waves are not typically seen in V1-V3. Their presence in these leads can be significant. The absence of pathological Q waves does not rule out acute infarction, especially in the early stages. The evolution of EKG changes, from hyperacute T waves to ST elevation, then Q waves and T wave inversion, provides a temporal sequence of the infarction process. Prompt recognition of STEMI, based on these EKG criteria, is crucial for activating reperfusion therapies like percutaneous coronary intervention (PCI) or fibrinolysis.

Differentiating STEMI from Mimics and Complex Cases

Covers: HOW-TO Recognize STEMI Mimics on 12-Lead EKG! (video, 25 min) · Sgarbossa's Criteria - HOW TO Identify AMI with LBBB on 12-lead EKG (video, 14 min)

Not all ST elevation indicates an acute myocardial infarction. Several conditions can 'mimic' STEMI on an EKG, leading to potential misdiagnosis and inappropriate treatment. It is essential to differentiate these mimics from true STEMI.

Common STEMI Mimics

1. **Early Repolarization (Benign Early Repolarization, BER):** Common in young, healthy individuals, especially athletes. Characterized by diffuse (widespread) ST elevation, often with a 'fishhook' or notching at the J point, and a concave (scooped) ST segment. T waves are typically tall and symmetrical. Unlike STEMI, BER is usually stable and not associated with symptoms of acute chest pain.
2. **Pericarditis:** Inflammation of the pericardium. Causes diffuse ST elevation, often with PR segment depression, particularly in leads II, aVF, V4-V6. The ST elevation is typically concave. Patients often report sharp, pleuritic chest pain that improves when leaning forward.
3. **Left Ventricular Hypertrophy (LVH) with Strain:** As discussed, LVH can cause ST depression and T wave inversion, primarily in lateral leads. However, in some cases, it can also cause subtle ST elevation that might be mistaken for STEMI. The overall pattern, including voltage criteria for LVH, helps differentiate.
4. **Left Bundle Branch Block (LBBB):** A complete LBBB significantly alters ventricular depolarization, making STEMI diagnosis challenging. The wide QRS complex and secondary ST-T changes (ST depression and T wave inversion in leads with upright QRS, and ST elevation in leads with downward QRS) can obscure or mimic STEMI. This warrants special criteria.
5. **Ventricular Paced Rhythm:** Paced rhythms also cause wide QRS complexes and secondary ST-T changes, similar to LBBB, making STEMI diagnosis difficult.
6. **Brugada Syndrome:** A genetic disorder characterized by specific EKG patterns in leads V1-V3 (coved type ST elevation followed by a negative T wave, or saddleback type ST elevation). It is associated with an increased risk of sudden cardiac death but is not an acute ischemic event.
7. **Hyperkalemia:** High potassium levels can cause tall, peaked T waves, which might be mistaken for hyperacute T waves of early STEMI. However, hyperkalemia also often presents with a widened QRS and flattened P waves.

Sgarbossa's Criteria for AMI with LBBB

When a patient presents with new or presumably new LBBB and symptoms suggestive of AMI, standard STEMI criteria are unreliable. Sgarbossa's criteria (and its modified versions) help identify acute ischemia in this challenging scenario. The original criteria assign points based on three findings:

1. **Concordant ST elevation of 1 mm or more in leads with a positive QRS complex.** (Score: 5 points) 'Concordant' means both the QRS and ST segment are in the same direction (both positive). This is highly specific for STEMI in LBBB.
2. **Concordant ST depression of 1 mm or more in leads V1-V3.** (Score: 3 points) This also indicates acute ischemia.
3. **Discordant ST elevation of 5 mm or more in leads with a negative QRS complex.** (Score: 2 points) 'Discordant' means the ST segment is opposite to the QRS direction. While some discordance is expected in LBBB, significant elevation suggests AMI.

A total score of 3 or more points suggests an AMI. However, the original criteria had low sensitivity. The **Modified Sgarbossa's Criteria (Smith-modified Sgarbossa)** improved sensitivity by replacing the third criterion. It focuses on the **ST/S ratio** in leads with a negative QRS complex. An ST elevation / S wave magnitude ratio of less than or equal to -0.25 (meaning the ST elevation is at least 25% of the depth of the S wave) in any lead with a negative QRS is highly indicative of STEMI in LBBB. This modification significantly enhances the ability to detect STEMI in the presence of LBBB without losing much specificity. Always consider the clinical context when applying these criteria.

The Complete 12-Lead EKG Masterclass: A Systematic Interpretation Method

Covers: The COMPLETE 12-Lead EKG Masterclass! (video, 4 hr 9 min)

A systematic approach to 12-lead EKG interpretation ensures that no critical findings are missed and allows for a comprehensive assessment of cardiac electrical activity. This structured method integrates all the concepts learned, from basic rhythm analysis to advanced ischemia and hypertrophy recognition. Consistency in your approach will build confidence and accuracy.

Here is a step-by-step systematic method for interpreting any 12-lead EKG:

1. **Patient Information and Context:** Always start by checking the patient's name, date, time of EKG, and any previous EKGs for comparison. Understand the clinical reason for the EKG. This context is vital for interpretation.
2. **Rate:** Calculate the heart rate. Use the 300-150-100-75-60-50 method for regular rhythms or count QRS complexes in a 6-second strip and multiply by 10 for irregular rhythms.
3. **Rhythm:** Determine the regularity of P waves and QRS complexes. Identify the presence and morphology of P waves, PR interval, and QRS duration. Based on these, classify the underlying rhythm (e.g., sinus rhythm, atrial fibrillation, ventricular tachycardia).
4. **Axis:** Determine the mean electrical axis of the QRS complex. A quick method involves looking at leads I and aVF. If both are positive, the axis is normal (0 to +90 degrees). If I is positive and aVF is negative, check lead II. If II is positive, axis is normal. If II is negative, it is Left Axis Deviation (LAD). If I is negative and aVF is positive, it is Right Axis Deviation (RAD). If both I and aVF are negative, it is Extreme Right Axis Deviation.
5. **Intervals:** Measure and assess the key intervals:
 - **PR Interval:** Normal is 0.12 to 0.20 seconds (3 to 5 small boxes). Prolongation indicates AV block.
 - **QRS Duration:** Normal is 0.06 to 0.10 seconds (1.5 to 2.5 small boxes). Widening suggests bundle branch block, ventricular rhythm, or aberrancy.
 - **QTc Interval:** Corrected QT interval. Normal varies by gender (e.g., < 450 ms for men, < 470 ms for women). Prolongation can indicate risk for arrhythmias.
6. **Hypertrophy:** Look for criteria for Left Ventricular Hypertrophy (LVH) or Right Ventricular Hypertrophy (RVH) using voltage criteria (e.g., Sokolow-Lyon, Cornell) and associated repolarization abnormalities (strain pattern) as discussed previously.

7. Ischemia, Injury, and Infarction: This is a critical step.

- **ST Segment:** Systematically examine the ST segment in all 12 leads. Look for elevation (STEMI criteria) or depression (ischemia). Pay attention to morphology (concave vs. convex).
 - **T Waves:** Assess T wave morphology. Look for inversion (ischemia), hyperacute T waves (early STEMI), or peaked T waves (hyperkalemia).
 - **Q Waves:** Identify any pathological Q waves (duration > 0.04s or depth > 1/3 R wave height) in contiguous leads, indicating prior infarction.
 - **Reciprocal Changes:** Look for ST depression in leads opposite to those with ST elevation, which strengthens the diagnosis of acute injury.
 - **STEMI Mimics:** If ST elevation is present, consider and rule out common mimics like early repolarization or pericarditis. Compare with previous EKGs if available.
 - **Bundle Branch Blocks:** If LBBB or ventricular pacing is present, apply Sgarbossa's criteria (original or modified) to assess for acute myocardial infarction.
- 8. Other Findings:** Look for any other abnormalities such as conduction blocks (e.g., fascicular blocks), electrolyte disturbances (e.g., U waves in hypokalemia), or drug effects (e.g., digoxin effect).
- 9. Clinical Correlation and Impression:** Synthesize all findings. Do the EKG changes correlate with the patient's symptoms and clinical picture? Formulate a concise EKG impression that summarizes the most significant findings. This systematic method ensures a thorough and accurate interpretation, crucial for effective patient management.

KEY TAKEAWAYS

- Ventricular hypertrophy, particularly LVH, is identified by increased voltage criteria and characteristic repolarization abnormalities known as a strain pattern.
- The ST segment and T wave are primary EKG indicators of myocardial ischemia, injury, and infarction, reflecting the heart muscle's oxygen supply and recovery.
- Myocardial ischemia typically presents with ST segment depression or T wave inversion in two or more contiguous leads.
- ST Elevation Myocardial Infarction (STEMI) is diagnosed by specific criteria for ST segment elevation in two or more contiguous leads, indicating acute transmural injury.
- Pathological Q waves signify irreversible myocardial necrosis and are a late sign of infarction.
- Several conditions can mimic STEMI on EKG; careful differentiation is crucial to avoid misdiagnosis and inappropriate treatment.
- Sgarbossa's criteria, especially the modified version, are essential tools for diagnosing acute myocardial infarction in the presence of Left Bundle Branch Block (LBBB).
- A systematic, step-by-step approach to 12-lead EKG interpretation ensures comprehensive analysis and accurate clinical assessment.

CHECK YOUR UNDERSTANDING

Answer these before moving on. Model answers are in the Answer Key at the back of this guide.

1. What are the key EKG criteria for Left Ventricular Hypertrophy (LVH), and what is a 'strain pattern'?
2. Describe the EKG changes associated with myocardial ischemia versus myocardial injury.
3. What specific EKG findings define an ST Elevation Myocardial Infarction (STEMI)?
4. Name three common conditions that can mimic STEMI on an EKG.
5. Why are Sgarbossa's criteria important, and what is the significance of the modified criteria?

CHAPTER 4

Reading the EKG Strip

Module 4 focuses on the fundamental principles of electrocardiogram (EKG) interpretation. You will first learn the heart's electrical conduction system and how each electrical event translates into a specific waveform on the EKG paper. Understanding this physiological basis is crucial for moving beyond simple pattern recognition.

Next, this chapter introduces a robust, six-step method for systematically analyzing any EKG strip. This method provides a consistent framework to identify rhythms, measure intervals, and detect critical changes, ensuring you approach every EKG with confidence and precision. By the end of this chapter, you will be equipped to interpret EKG strips methodically, connecting the electrical activity to its visual representation.

The Heart's Electrical System and EKG Waveforms

Covers: The Electrical path of a Heartbeat

An electrocardiogram (EKG) records the electrical signals that command the heart's muscle contractions. It is not a direct picture of the heart squeezing. Instead, it graphs the electrical impulses moving through the heart. Understanding this electrical path makes every waveform on the EKG strip a meaningful landmark.

The Conduction System and EKG Waveforms

The heart's electrical activity begins with specialized cells that generate and conduct impulses. This system follows a specific pathway:

1. **Sinoatrial (SA) Node:** Located in the right atrium, the SA node is the heart's natural pacemaker. It typically fires 60 to 100 times per minute at rest. This impulse initiates the heartbeat.
2. **Atrial Depolarization (P Wave):** The electrical impulse spreads rapidly across both the right and left atria. This causes the atria to contract. On the EKG, this atrial contraction is represented by the **P wave**, a small, rounded upward deflection.
3. **Atrioventricular (AV) Node Delay (PR Interval):** The impulse reaches the atrioventricular (AV) node, located between the atria and ventricles. The AV node deliberately slows the signal for approximately 0.10 seconds. This crucial delay allows the ventricles to fully fill with blood before they contract. This delay and the time it takes for the impulse to travel from the SA node through the atria to the AV node are reflected in the **PR interval**. A normal PR interval measures 0.12 to 0.20 seconds.
4. **Ventricular Depolarization (QRS Complex):** After the AV node delay, the signal races down the **bundle of His**, splits into the **right and left bundle branches**, and then fans out through the **Purkinje fibers**. This rapid conduction system quickly depolarizes the ventricles, causing them to contract and pump blood out of the heart. This ventricular depolarization is represented by the **QRS complex**, a sharp, tall deflection. A normal QRS complex is narrow, measuring less than 0.12 seconds.

A wide QRS complex suggests the electrical signal took a slower, abnormal path through the ventricular muscle rather than the efficient conduction system.

5. **Ventricular Repolarization (T Wave):** After contracting, the ventricles electrically reset themselves, preparing for the next beat. This process of repolarization is represented by the **T wave**, a rounded upward deflection that follows the QRS complex.

Backup Pacemakers

The heart's electrical system has built-in redundancy. If the SA node fails or slows significantly, other parts of the conduction system can take over as backup pacemakers, albeit at slower rates:

- The **AV junction** (around the AV node) can pace the heart at 40 to 60 beats per minute.
- The **ventricles themselves** can generate impulses, but only at a very slow rate of 20 to 40 beats per minute.

These backup rates provide important clues about the origin of a heart rhythm. For example, a regular rhythm at 45 beats per minute with absent P waves strongly suggests the rhythm is originating from the AV junction rather than a normally functioning SA node.

EKG Paper as a Ruler

EKG paper is precisely calibrated to allow accurate measurement of time and voltage. The paper moves at a standard speed of 25 millimeters per second. Each small square on the EKG grid represents 0.04 seconds horizontally. Five small squares make up one large square, which therefore represents 0.20 seconds (5×0.04 s). Vertically, the squares measure voltage. Because the paper acts as a ruler, you can measure the duration of waves and intervals, and calculate the heart rate. For instance, to estimate a regular heart rate, you can count the number of large boxes between two consecutive R waves and divide 300 by that number. For irregular rhythms, you count the number of QRS complexes in a 6-second strip and multiply by 10.

Understanding what each wave and interval *means* physiologically is more valuable than simply memorizing rhythm names. When you know the P wave signifies atrial contraction and the PR interval represents the AV node's delay, a prolonged PR interval immediately tells you the AV node is slowing the signal more than usual, which is the essence of a first-degree AV block.

A Systematic Approach to EKG Interpretation

Covers: A Six-Step Method for Any Strip

Interpreting an EKG strip requires a consistent, systematic approach. Experienced clinicians use a reliable checklist every time, ensuring no critical details are missed. This six-step method provides that structure and should be applied to every EKG strip until it becomes automatic.

The Six-Step Method for EKG Interpretation

1. **Rate:** Determine the heart rate. A normal heart rate is typically 60 to 100 beats per minute (bpm). A rate below 60 bpm is called bradycardia, and a rate above 100 bpm is tachycardia.

- **For regular rhythms:** Use the '300 method'. Count the number of large boxes between two consecutive R waves and divide 300 by that number. For example, if there are 3 large boxes, the rate is $300 / 3 = 100$ bpm. Common sequences to memorize are 300, 150, 100, 75, 60, 50 for 1, 2, 3, 4, 5, 6 large boxes respectively.
 - **For irregular rhythms:** Use the '6-second method'. Locate a 6-second strip (usually marked by 3-second tick marks or 30 large boxes). Count the number of QRS complexes within that 6-second strip and multiply by 10. For example, if you count 7 QRS complexes in 6 seconds, the rate is $7 \times 10 = 70$ bpm.
2. **Regularity:** Assess the rhythm's regularity. Use calipers or a piece of paper to march out the R-R intervals (the distance between consecutive R waves). Compare several intervals.
 - **Regular:** R-R intervals are consistent.
 - **Regularly Irregular:** There is a repeating pattern to the irregularity.
 - **Irregularly Irregular:** There is no discernible pattern to the R-R intervals, often seen in atrial fibrillation.
 3. **P Waves:** Examine the P waves. Are they present? Do they all look uniform (the same shape and size)? Is there one P wave before every QRS complex? Abnormal findings, such as absent P waves, a sawtooth pattern (atrial flutter), or a chaotic, fibrillating baseline (atrial fibrillation), indicate a rhythm that is not originating from the SA node.
 4. **PR Interval:** Measure the PR interval, from the beginning of the P wave to the beginning of the QRS complex. A normal PR interval is 0.12 to 0.20 seconds. Deviations can indicate blocks:
 - **Prolonged and constant PR interval:** Suggests a first-degree AV block.
 - **Progressively lengthening PR interval until a QRS complex is dropped:** This pattern is characteristic of Wenckebach (Mobitz Type I) second-degree AV block.
 - **Constant PR interval with random, intermittently dropped QRS complexes:** This is Mobitz Type II second-degree AV block, a more serious condition that often requires immediate medical attention.
 - **No consistent relationship between P waves and QRS complexes:** Indicates a third-degree (complete) AV block, where atria and ventricles beat independently.
 5. **QRS Width:** Measure the duration of the QRS complex. A normal QRS complex is narrow, less than 0.12 seconds. A narrow QRS typically indicates that the impulse originated above the ventricles (supraventricular origin). A wide QRS complex (0.12 seconds or greater) suggests either a ventricular origin for the impulse or aberrant conduction (an abnormal pathway) within the ventricles.
 6. **QT Interval and Everything Else:** Evaluate the QT interval, which represents the total time for ventricular depolarization and repolarization. A corrected QT (QTc) interval over approximately 500 milliseconds (ms) can increase the risk of a dangerous arrhythmia called Torsades de Pointes. Also, scan the ST segment for elevation or depression, and note any abnormal T wave changes, as these can indicate myocardial ischemia or injury.

Rhythms You Must Never Miss

Some rhythms demand immediate recognition and intervention. These include:

- **Ventricular Fibrillation (VFib):** Characterized by chaotic, disorganized electrical activity with no recognizable QRS complexes. The heart is merely quivering, not pumping blood. There is no pulse. Immediate defibrillation is required.
- **Ventricular Tachycardia (VTach):** Appears as a wide, fast, and usually regular rhythm. If the patient has no pulse, it is treated as a medical emergency similar to VFib.
- **Third-Degree (Complete) AV Block:** The atria and ventricles beat independently, leading to a slow and often unstable heart rate. This rhythm often requires pacing.
- **Asystole:** A flat line on the EKG, indicating no electrical activity. Always confirm asystole in a second EKG lead and check electrode placement before confirming, as a loose lead can mimic this rhythm.

Treat the Patient, Not the Monitor

Always correlate EKG findings with the patient's clinical condition. EKG artifact (interference) can mimic serious arrhythmias. For example, patient movement or electrical interference can make a normal rhythm appear like ventricular tachycardia. Conversely, a patient who looks unwell (pale, sweaty, hypotensive) with a seemingly benign EKG rhythm is still an emergency. Your clinical decision should always integrate the EKG rhythm with the patient's physical signs and symptoms.

KEY TAKEAWAYS

- An EKG records the heart's electrical signals, not its mechanical contractions, with each waveform representing a specific electrical event.
- The heart's electrical impulse originates in the SA node, spreads through the atria (P wave), pauses at the AV node (PR interval), then depolarizes the ventricles (QRS complex), and finally repolarizes (T wave).
- EKG paper acts as a ruler, with small boxes representing 0.04 seconds and large boxes representing 0.20 seconds, allowing precise measurement of rates and intervals.
- A systematic six-step method (rate, regularity, P waves, PR interval, QRS width, QT interval/other changes) ensures consistent and accurate EKG interpretation.
- Understanding normal values for rate and intervals (e.g., PR 0.12-0.20s, QRS <0.12s) is crucial for identifying abnormalities.
- Certain rhythms, such as ventricular fibrillation, pulseless ventricular tachycardia, and third-degree AV block, require immediate recognition and intervention.
- Always assess the patient's clinical status in conjunction with the EKG findings, as artifact can mimic serious rhythms and a 'clean' EKG does not always mean a stable patient.

CHECK YOUR UNDERSTANDING

Answer these before moving on. Model answers are in the Answer Key at the back of this guide.

1. Describe the electrical path of a heartbeat and how each major event is represented on an EKG.
2. What are the normal durations for the PR interval and QRS complex, and what do deviations from these norms suggest?
3. Explain the '300 method' for calculating heart rate and when it is appropriate to use.
4. List the first three steps of the systematic EKG interpretation method and what each step assesses.
5. Why is it critical to 'treat the patient, not the monitor' when interpreting EKG strips?

CHAPTER 5

Final Assessment: EKG Interpretation

This chapter serves as your final checkpoint in the EKG Basics course. It is designed to help you consolidate all the knowledge and skills you have acquired throughout the previous modules. Here, you will apply your understanding of cardiac electrophysiology, rhythm analysis, and 12-lead interpretation to a comprehensive assessment.

Think of this assessment not just as a test, but as a valuable learning opportunity. It will highlight your strengths and pinpoint any areas where further review may be beneficial. Approaching this material with a focused, systematic mindset will ensure you gain the most from this crucial final step.

Mastery Check: What You Should Know by Now

Covers: Final Assessment: EKG Interpretation (quiz, 5 min)

By this point in the course, you should have a solid grasp of fundamental EKG interpretation. You should be able to:

- Explain the heart's electrical conduction system and the specific cardiac events each EKG waveform (P wave, QRS complex, T wave) represents.
- Systematically measure heart rate, rhythm regularity, PR interval, QRS duration, and QT interval on any EKG strip.
- Confidently identify common sinus rhythms, various heart blocks, and potentially lethal arrhythmias.
- Apply a repeatable, methodical approach to interpreting a 12-lead EKG, including axis determination and identifying ischemia or infarction patterns.

Your goal is not merely to memorize patterns, but to understand the underlying physiology that produces them. This conceptual understanding allows for accurate interpretation even with variations.

Approaching the Final Assessment

Covers: Final Assessment: EKG Interpretation (quiz, 5 min)

Success on the final assessment, and in real-world EKG interpretation, relies on a consistent, disciplined approach. Treat each question as a clinical scenario requiring your full attention.

1. **Read Carefully:** Pay close attention to all provided information, including any patient context or specific instructions.
2. **Apply the 5-Step Method:** Do not skip steps. Systematically assess rate, rhythm, P waves, PR interval, QRS complex, and T waves. This prevents overlooking critical details.

3. **Trust Your Method:** Avoid second-guessing your initial systematic interpretation unless you find clear evidence to contradict it. Stick to the process you have practiced.
4. **Manage Your Time:** While this quiz is short, practice efficient interpretation. Do not dwell too long on a single question if you are truly stuck. Move on and return if time permits.
5. **Stay Calm:** If you encounter a challenging strip, take a breath. Reapply your systematic approach from the beginning. Panic can lead to errors.

Common Pitfalls and How to Avoid Them

Covers: Final Assessment: EKG Interpretation (quiz, 5 min)

Many students encounter similar challenges when interpreting EKGs. Awareness of these common mistakes can help you avoid them.

- **Rushing the Interpretation:** Skipping steps in the systematic approach often leads to misidentification. Take your time with each component.
- **Ignoring Subtle Clues:** Small changes in waveform morphology, interval duration, or rhythm regularity can be diagnostic. Look closely at every detail.
- **Misinterpreting Artifact:** Electrical interference or patient movement can mimic arrhythmias. Look for consistency in patterns across the strip. True cardiac activity usually maintains a more regular, physiological appearance.
- **Focusing on a Single Lead:** Especially with 12-lead EKGs, avoid making a diagnosis based on one lead. Correlate findings across multiple leads to confirm patterns.
- **Lack of Practice:** EKG interpretation is a skill that improves with repetition. Consistent practice builds speed and accuracy.
- **Panic and Overthinking:** When faced with a complex strip, some students abandon their method. Revert to your systematic approach to break down the complexity.

Interpreting Your Results

Covers: Final Assessment: EKG Interpretation (quiz, 5 min)

Your score on the final assessment is only one part of the learning process. The true value lies in understanding *why* you answered questions correctly or incorrectly.

1. **Review All Answers:** Do not just look at your score. Go through every question, especially those you answered incorrectly.
2. **Identify Your Weaknesses:** For each wrong answer, determine the root cause. Was it a conceptual misunderstanding of an arrhythmia? A calculation error for rate or intervals? Did you miss a specific waveform characteristic? Was it difficulty with 12-lead localization?
3. **Targeted Review:** Once you identify patterns in your mistakes, revisit the specific lessons or sections of this study guide that cover those topics. For example, if you struggled with heart blocks, review Module 3, Lesson 14.

4. **Reinforce Strengths:** Correct answers also provide valuable feedback. They confirm your understanding and build confidence in those areas.
5. **Practice More:** Use additional practice strips or quizzes to solidify your understanding in identified weak areas. Repetition is key to mastery.

This assessment is a diagnostic tool. Use its feedback to refine your knowledge and become a more confident EKG interpreter.

KEY TAKEAWAYS

- The final assessment evaluates your comprehensive understanding of EKG interpretation principles.
- Always approach each EKG strip systematically, applying the learned 5-step method consistently.
- Avoid common mistakes such as rushing, inconsistent methodology, or misinterpreting artifact on the tracing.
- Thoroughly review all assessment questions, especially incorrect answers, to identify specific knowledge gaps.
- Use your assessment results to guide further targeted study and reinforce areas needing improvement.
- Confidence in EKG interpretation develops through consistent practice and a deep understanding of cardiac electrophysiology.

CHECK YOUR UNDERSTANDING

Answer these before moving on. Model answers are in the Answer Key at the back of this guide.

1. What are the key components of the heart's conduction system you should be able to explain, and what EKG waveforms do they correspond to?
2. Describe the systematic approach for interpreting an EKG strip.
3. Name three common pitfalls students encounter during EKG interpretation and how to avoid them.
4. How should you use your results from the final assessment to improve your EKG interpretation skills?
5. What is artifact on an EKG, and why is it important to recognize?

REFERENCE

Glossary

12-lead ekg

An electrocardiogram recording using 10 electrodes to produce 12 different electrical views of the heart.

Arrhythmia

Any deviation from the normal sinus rhythm of the heart, characterized by an irregular heart rate, rhythm, or conduction pattern.

Artifact

Electrical interference or noise on an EKG tracing that is not cardiac in origin, potentially mimicking actual heart activity.

Atrial enlargement

An increase in the size of the atria, detectable by specific P wave changes on an EKG.

Atrial fibrillation (afib)

A chaotic atrial arrhythmia characterized by an irregularly irregular ventricular rhythm and absent P waves, replaced by fibrillatory waves.

Av node (atrioventricular node)

A specialized group of cells that delays the electrical impulse from the atria before it passes to the ventricles, allowing for ventricular filling.

Bradycardia

A heart rate below 60 beats per minute.

Bundle branch block

A delay or obstruction of electrical impulses along the bundle branches, causing a widened QRS complex.

Cardiac axis

The predominant direction of electrical activity during ventricular depolarization, typically measured in degrees.

Conduction system

The specialized network of cardiac cells that generate and transmit electrical impulses throughout the heart.

Contiguous leads

EKG leads that view the same anatomical area of the heart, important for identifying localized changes like ischemia or infarction.

Coronary arteries

The blood vessels that supply oxygenated blood to the heart muscle itself.

Interval

The measured duration between two specific points on an EKG tracing, such as the PR interval or QT interval, indicating the time taken for electrical events.

Left axis deviation (lad)

A cardiac axis shifted to the left, often indicating conditions like left ventricular hypertrophy or inferior MI.

Myocardial ischemia

A reversible condition where heart muscle receives insufficient blood flow, typically manifesting as ST depression or T wave inversion.

P wave

The first deflection on an EKG, representing atrial depolarization (contraction).

Pathological q wave

A Q wave that is abnormally wide ($>0.04s$) or deep ($>1/3$ R wave height), indicating irreversible myocardial necrosis (infarction).

Pr interval

The time from the beginning of the P wave to the beginning of the QRS complex, representing atrial depolarization and AV nodal delay, normally 0.12 to 0.20 seconds.

Qrs complex

The prominent deflection on an EKG, representing ventricular depolarization (contraction), typically lasting 0.06 to 0.12 seconds.

Right axis deviation (rad)

A cardiac axis shifted to the right, often associated with right ventricular hypertrophy or pulmonary embolism.

Sa node

Sinoatrial node, the heart's natural pacemaker, located in the right atrium, typically initiating impulses at 60 to 100 bpm.

Sa node (sinoatrial node)

The heart's natural pacemaker, located in the right atrium, typically firing 60 to 100 times per minute.

Sgarbossa's criteria

A set of EKG criteria used to diagnose acute myocardial infarction in the presence of a Left Bundle Branch Block (LBBB).

St elevation myocardial infarction (STEMI)

A type of heart attack characterized by significant ST segment elevation on the EKG, indicating acute transmural myocardial injury.

St segment

The isoelectric portion of the EKG between the end of the QRS complex (J point) and the beginning of the T wave, representing ventricular repolarization.

Systematic interpretation

A structured, step-by-step approach to analyzing EKG strips, ensuring all critical components are evaluated.

T wave

The EKG waveform representing ventricular repolarization, typically upright and asymmetrical.

Tachycardia

A heart rate above 100 beats per minute.

Third-degree av block

Complete heart block where no atrial impulses are conducted to the ventricles, resulting in independent atrial and ventricular rhythms.

Ventricular hypertrophy

Thickening of the muscular walls of the heart's ventricles, often due to increased workload.

Ventricular tachycardia (vt)

A rapid, regular ventricular rhythm with wide, bizarre QRS complexes, often a precursor to ventricular fibrillation.

Waveform

The distinct deflections (P wave, QRS complex, T wave) seen on an EKG tracing, each representing a specific electrical event in the heart.

REFERENCE

Answer Key

Chapter 1: ECG Foundations

1. Describe the normal electrical pathway through the heart, starting from the SA node.

The electrical impulse begins at the SA node, spreads across the atria, then reaches the AV node where it is delayed. From the AV node, it travels down the Bundle of His, through the bundle branches, and into the Purkinje fibers, causing ventricular contraction.

2. What EKG waveform or interval corresponds to atrial depolarization, ventricular depolarization, and ventricular repolarization?

Atrial depolarization is represented by the P wave. Ventricular depolarization is represented by the QRS complex. Ventricular repolarization is represented by the T wave.

3. You see an EKG strip with an atrial rate of 300 bpm and a ventricular rate of 150 bpm, with a 'sawtooth' baseline. What rhythm is this, and what is the AV conduction ratio?

This describes Atrial Flutter. The sawtooth baseline is characteristic of flutter waves. With an atrial rate of 300 bpm and a ventricular rate of 150 bpm, the AV conduction ratio is 2:1, meaning two atrial impulses occur for every one ventricular impulse.

4. A patient's EKG shows a regular rhythm, a heart rate of 55 bpm, and all other EKG parameters (P waves, PR interval, QRS duration) are within normal limits. What is the most likely rhythm?

The most likely rhythm is Sinus Bradycardia. All criteria for normal sinus rhythm are met, except for the heart rate, which is below 60 bpm.

5. What are the key EKG characteristics that differentiate a first-degree AV block from a second-degree AV block Type I (Wenckebach)?

First-degree AV block shows a consistently prolonged PR interval (greater than 0.20 seconds) with every P wave followed by a QRS. Second-degree AV block Type I (Wenckebach) is characterized by a progressively lengthening PR interval until a QRS complex is dropped.

Chapter 2: 12-Lead EKG Interpretation

1. Describe the primary function of the coronary circulation and how it relates to EKG interpretation.

The coronary circulation supplies oxygen and nutrients to the heart muscle. When this supply is inadequate, such as in ischemia or infarction, the heart muscle cells are damaged. This damage alters their electrical activity, which is then reflected as specific changes on the EKG, such as ST segment deviations or T wave inversions.

2. What are the main components of the heart's electrical conduction system, and what is the role of each?

The main components are the SA node, AV node, Bundle of His, bundle branches, and Purkinje fibers.

The SA node is the primary pacemaker. The AV node delays the impulse to allow ventricular filling. The Bundle of His, bundle branches, and Purkinje fibers rapidly transmit the impulse throughout the ventricles, ensuring coordinated contraction.

3. Outline the basic systematic steps for interpreting a 12-lead EKG.

A systematic approach typically includes determining the heart rate, analyzing the rhythm for regularity and P waves, measuring intervals (PR, QRS, QT), assessing cardiac axis, checking for hypertrophy or enlargement, and finally, evaluating for ischemia, injury, or infarction. Consistency in this method helps prevent missed findings.

4. How do you identify a Right Bundle Branch Block (RBBB) on a 12-lead EKG?

RBBB is characterized by a widened QRS complex, typically 0.12 seconds or greater. Key morphological changes include an RSR' pattern (or "M" shape) in lead V1 and a wide, slurred S wave in leads I and V6. These findings indicate a delay in the depolarization of the right ventricle.

5. Explain the significance of cardiac axis deviation.

Cardiac axis represents the overall direction of ventricular depolarization. A normal axis falls between -30 and +90 degrees. Deviations, such as left axis deviation (LAD) or right axis deviation (RAD), can indicate underlying conditions like ventricular hypertrophy, myocardial infarction, or conduction defects. Assessing axis helps in localizing pathology.

Chapter 3: 12-Lead EKG Interpretation

1. What are the key EKG criteria for Left Ventricular Hypertrophy (LVH), and what is a 'strain pattern'?

Key EKG criteria for LVH include the Sokolow-Lyon criteria (S wave in V1/V2 + R wave in V5/V6 > 35 mm) and Cornell criteria (R in aVL + S in V3 > 28 mm for men, > 20 mm for women). A 'strain pattern' refers to secondary repolarization abnormalities seen in LVH, characterized by downsloping ST segment depression and asymmetrical T wave inversion, typically in lateral leads.

2. Describe the EKG changes associated with myocardial ischemia versus myocardial injury.

Myocardial ischemia, a reversible state, typically manifests as ST segment depression (horizontal or downsloping) or T wave inversion. Myocardial injury, a more severe and acute condition, is characterized by ST segment elevation. Both changes occur in contiguous leads and indicate inadequate blood flow to the heart muscle.

3. What specific EKG findings define an ST Elevation Myocardial Infarction (STEMI)?

STEMI is defined by significant ST segment elevation in two or more contiguous leads. The criteria for ST elevation vary by lead, with higher thresholds (≥ 2 mm in men ≥ 40 , ≥ 2.5 mm in men < 40 , ≥ 1.5 mm in women) in leads V2-V3, and ≥ 1 mm in all other leads. Pathological Q waves may develop later, indicating infarction.

4. Name three common conditions that can mimic STEMI on an EKG.

Three common conditions that can mimic STEMI are Benign Early Repolarization (BER), Pericarditis, and Left Bundle Branch Block (LBBB). BER shows diffuse, concave ST elevation with a J-point notch.

Pericarditis presents with diffuse, concave ST elevation and often PR depression. LBBB causes wide QRS complexes and secondary ST-T changes that can obscure or mimic STEMI.

5. Why are Sgarbossa's criteria important, and what is the significance of the modified criteria?

Sgarbossa's criteria are crucial for diagnosing acute myocardial infarction in patients with a Left Bundle Branch Block (LBBB), as LBBB significantly complicates standard STEMI diagnosis. The original criteria identify specific concordant or markedly discordant ST changes. The modified Sgarbossa's criteria, particularly the ST/S ratio, improve the sensitivity for detecting STEMI in LBBB, making it a more reliable tool for clinical decision-making.

Chapter 4: Reading the EKG Strip

1. Describe the electrical path of a heartbeat and how each major event is represented on an EKG.

The electrical impulse begins at the SA node, causing atrial depolarization, which is seen as the P wave. The signal then pauses at the AV node, reflected in the PR interval. Next, it rapidly depolarizes the ventricles, forming the QRS complex. Finally, the ventricles repolarize, represented by the T wave.

2. What are the normal durations for the PR interval and QRS complex, and what do deviations from these norms suggest?

A normal PR interval is 0.12 to 0.20 seconds. A prolonged PR interval may indicate an AV block. A normal QRS complex is less than 0.12 seconds. A wide QRS complex suggests either a ventricular origin for the impulse or aberrant conduction within the ventricles.

3. Explain the '300 method' for calculating heart rate and when it is appropriate to use.

The 300 method is used for regular rhythms. You count the number of large boxes between two consecutive R waves and divide 300 by that number. For example, if there are 4 large boxes between R waves, the rate is $300 / 4 = 75$ bpm.

4. List the first three steps of the systematic EKG interpretation method and what each step assesses.

The first three steps are Rate, Regularity, and P waves. Rate assesses the heart's speed (normal 60-100 bpm). Regularity determines if the R-R intervals are consistent, regularly irregular, or irregularly irregular. P waves assess their presence, uniformity, and relationship to the QRS complex, indicating atrial activity.

5. Why is it critical to 'treat the patient, not the monitor' when interpreting EKG strips?

It is critical because EKG artifact can mimic life-threatening rhythms, leading to unnecessary interventions. Conversely, a patient who is clinically unstable may have a seemingly normal EKG. Always correlate EKG findings with the patient's physical symptoms and overall condition to make appropriate clinical decisions.

Chapter 5: Final Assessment: EKG Interpretation

1. What are the key components of the heart's conduction system you should be able to explain, and what EKG waveforms do they correspond to?

You should be able to explain the SA node, AV node, Bundle of His, bundle branches, and Purkinje fibers. The P wave corresponds to atrial depolarization (SA node firing). The QRS complex corresponds to ventricular depolarization (Bundle of His, bundle branches, Purkinje fibers). The T wave corresponds to ventricular repolarization.

2. Describe the systematic approach for interpreting an EKG strip.

The systematic approach involves five steps: first, determine the heart rate. Second, assess the rhythm for regularity. Third, analyze the P waves for presence and morphology. Fourth, measure the PR interval and QRS duration. Fifth, examine the T waves and overall ST segment. This method ensures all critical aspects are evaluated.

3. Name three common pitfalls students encounter during EKG interpretation and how to avoid them.

Common pitfalls include rushing the interpretation, which can be avoided by consistently applying the 5-step method. Another is misinterpreting artifact, which requires careful observation for consistent patterns versus irregular noise. A third is overlooking subtle clues; this is addressed by meticulously examining all waveforms and intervals for any deviations from normal.

4. How should you use your results from the final assessment to improve your EKG interpretation skills?

Do not just look at the score. Review every question, especially incorrect ones, to understand the specific reasons for error. Identify patterns in your mistakes, such as consistent difficulty with a particular arrhythmia or measurement. Then, revisit the relevant course modules or study guide sections for targeted review and additional practice in those identified weak areas.

5. What is artifact on an EKG, and why is it important to recognize?

Artifact is electrical interference on an EKG tracing that does not originate from the heart. It can be caused by patient movement, muscle tremors, or electrical noise from equipment. It is crucial to recognize artifact because it can mimic serious arrhythmias or obscure true cardiac activity, leading to misdiagnosis or inappropriate interventions. Distinguishing artifact from actual cardiac rhythms ensures accurate interpretation.

CLOSING

Where to Go Next

After completing "EKG Basics: Rhythm and 12-Lead Interpretation," you will possess a strong foundation in reading and understanding EKGs. To consolidate your skills, continue practicing with various EKG strips and 12-lead tracings. Seek opportunities to apply your knowledge in simulations or supervised clinical settings, if appropriate for your role.

Consider exploring advanced cardiology topics or specialized arrhythmia management courses to further expand your expertise. Subjects like advanced cardiac life support (ACLS) often build upon the EKG interpretation skills gained here. Consistent practice and continued learning are key to becoming proficient in this critical area of healthcare.

Remember the course disclaimer: this content is for educational purposes only and does not substitute for professional medical advice or clinical certification. Always adhere to professional guidelines and seek appropriate supervision for clinical practice.



MEGACOURSE

Learn Anything. Achieve Everything.

Track your progress, take the quizzes, and earn your certificate for this course at
megacourse.app/courses/ekg-basics-rhythm-and-12-lead-interpretation